Preparing your PhysiCell model to share on nanoHUB



Randy Heiland



@PhysiCell

PhysiCell Project

July 25-31, 2021



Overview

nanoHUB (https://nanohub.org/) is an open and free platform for computational research, education, and collaboration in nanotechnology, materials science, and related fields.

nanoHUB lets users run interactive apps from a browser.

 This tutorial will explain how you port an existing PhysiCell 2-D model to run on nanoHUB.

Assumptions

- You have installed the Anaconda Python distribution:
 - https://github.com/MathCancer/PhysiCell/blob/master/documentation/Quickstart.md#python
 - If you need more setup details: https://github.com/physicell-training/ws2021#pre-workshop-materials
- You have a working PhysiCell 2-D model that adheres to the default directory structure, file naming scheme (Makefile, main.cpp, config/PhysiCell_settings.xml), and contains the output/initial.xml file from a simulation.
- You have downloaded and installed (unzipped) the latest release from https://github.com/PhysiCell-Tools/PhysiCell-Jupyter-GUI/releases


Detailed instructions

- Follow the steps here:
 - https://github.com/PhysiCell-Tools/PhysiCell-Jupyter-GUI/blob/master/README.md

The following slides try to illustrate these steps.

- https://github.com/PhysiCell-Tools/PhysiCell-Jupyter-GUI/blob/master/README.md#steps-to-follow
 - ♦ Instead of using "ise_proj1", you may want to use: "pc4ws21teamN" (PhysiCell for Workshop 2021, where N=1,2,etc (whatever your team # is)) see next slide
- These instructions should let you create a Jupyter notebook that you can run locally (on <u>your</u> computer) before installing it on nanoHUB.
- Creating a nanoHUB app is considered optional (https://github.com/PhysiCell-Tools/PhysiCell-Jupyter-GUI/blob/master/README.md#create-a-nanohub-tool-optional), but we are assuming you will do it in this tutorial. Let us know if you need help.

Create a new GitHub repo for your nanoHUB project. E.g., I created "pc4ws21team42"





Create repository

PhysiCell Project
PhysiCell.org
PhysiCell

Using biorobots as an example (1)

```
~$ unzip PhysiCell V.1.9.0.zip
~$ mv PhysiCell PhysiCell v1.9.0
~$ cd PhysiCell_v1.9.0
~/PhysiCell_v1.9.0$ make biorobots-sample
cp./sample projects/biorobots/custom modules/* ./custom modules/
touch main.cpp && cp main.cpp main-backup.cpp
cp./sample_projects/biorobots/main-biorobots.cpp./main.cpp
cp Makefile Makefile-backup
cp./sample projects/biorobots/Makefile.
cp./config/PhysiCell_settings.xml./config/PhysiCell_settings-backup.xml
cp ./sample projects/biorobots/config/* ./config/
~/PhysiCell v1.9.0$ make
~/PhysiCell v1.9.0$ biorobots
... Let it run just for a very brief time (to generate some initial output) and then ctl-c to kill it
```

Using biorobots as an example (2)

Verify you have these 4 critical files:

```
~/PhysiCell_v1.9.0$ Is Makefile main.cpp config/PhysiCell_settings.xml output/initial.xml
Makefile main.cpp
config/PhysiCell settings.xml output/initial.xml
```

Clone your GitHub repo

~\$ git clone git@github.com:rheiland/pc4ws21team42.git

Cloning into 'pc4ws21team42'...

remote: Enumerating objects: 3, done.

remote: Counting objects: 100% (3/3), done.

remote: Total 3 (delta 0), reused 0 (delta 0), pack-reused 0

Receiving objects: 100% (3/3), done.

~\$

~/PhysiCell-Jupyter-GUI-1.4\$ python setup_new_proj.py ~/pc4ws21team42 ~/PhysiCell_v1.9.0 pc4ws21team42

• • •

This will generate these files in your cloned nanoHUB project:

```
~/pc4ws21team42$ Is
```

LICENSE examples/ rappture/
README.md make_my_tool.py src/
bin/ middleware/ tmpdir/

data/ mod makefile.py

doc/ pc4ws21team42.ipynb ← This will be your project's name




Test your notebook on your computer


Have a Web browser running, then run the following command from a shell:

~/pc4ws21team42\$ jupyter notebook pc4ws21team42.ipynb

You should see this Jupyter notebook displayed in your browser:




Click the 'Cell' menu, 'Run All', wait for each notebook "cell" to execute...




You should see a similar looking notebook for your project.

Now or later: You can leave this running, then edit the doc/about.html file to update this page's contents and (see next page).




After editing the "doc/about.html", Click the 'Kernel' menu, 'Restart & Run All', then click the pop-up button to confirm:






The notebook will refresh, showing your edited text:



Explore the other tabs of the GUI (but disregard the Animate tab)



Final steps for nanoHUB app

- If your local Jupyter notebook looks correct, you have the option of compiling your project and making sure you can Run it from the notebook - rf. Steps 4 and 5 in:
- https://github.com/PhysiCell-Tools/PhysiCell-Jupyter-GUI/blob/master/README.md#steps-to-follow

- However, you can probably skip straight to getting it ready to test on nanoHUB:
- https://github.com/PhysiCell-Tools/PhysiCell-Jupyter-GUI/blob/master/README.md#create-a-nanohub-tool-optional (not "optional" if you plan to do it ©)

Support

- We encourage you to join and actively use the <u>PhysiCell community</u>
 <u>Slack channel</u>. There, you can post questions (<u>#troubleshooting</u>), answer questions, and (hopefully) share successful modeling stories.
- Alternatively, you can submit problem tickets at https://sourceforge.net/p/physicell/tickets/
- Finally, please follow us on Twitter <u>@PhysiCell</u> and <u>@MathCancer</u>.

Funding Acknowledgements







PhysiCell Development:

- Breast Cancer Research Foundation
- Jayne Koskinas Ted Giovanis Foundation for Health and Policy
- National Cancer Institute (U01CA232137)
- National Science Foundation (1720625)

Training Materials:

Administrative supplement to NCI U01CA232137 (Year 2)